

VI.6.4-PRDUTIL-SYSTEM-DUMPTS PROGRAM PRDUTIL COMMAND DUMPTS

Purpose

Command DUMPTS prints time series header and data information from the Processed Data Base.

Input Data

<u>Card</u>	<u>Field</u>	<u>Format</u>	<u>Contents</u>
1	1		'@DUMPTS'
2	1	A8	Time series identifier
	2	A4	Time series data type code <u>1</u> /
	3	I	Julian hour of start of data: 0 = get from header
		or	
		A	'FUTURE' to print future time series header
	4	I	Desired data time interval: 0 = get from header
	5	I	Number of data values to be printed: 0 = get from header
	6	A	Units in which data are to be printed
	7	R	Value to be used to print missing data
	8	A	'FUTURE' to print future time series data
3	1		'END'

Note:

1/ If only 2 fields are entered then header information for regular time series is printed.

If only 3 fields are entered then header information for future time series is printed.

If 7 fields are entered then header information and time series data are printed for regular time series.

If 8 fields are entered then header information and time series data are printed for future time series.

Examples

```
@DUMPTS
TS1 MAP
TS1 MAP FUTURE
TS1 MAP 835314 6 44 IN -999.
TS1 MAP 0 0 0 IN -999. FUTURE
END
```